Subject: iTools questions
Posted by rivers on Thu, 28 Aug 2003 22:05:59 GMT
View Forum Message <> Reply to Message

I've started to work with the iTools, and they look great. I have a q question I wonder if anyone can help me with.

If I create an instance of an iTool, for example, iImage, how can I force the iTool to display a new data set from my application (or from the IDL command line for that matter)? For example:

IDL> a = dist(100) IDL> ilmage, a, ident=id IDL> b = dist(256)

Now I would like to display "b" in my ilmage. I don't want to use the File/Import/IDL Variable, I want to be able to do this via an IDL procedure or function call. If I have the object reference for the oParmSet that ilmage creates as IDL variable I can do it easily.

I have tested this by creating a modified version of ilmage that passes back oParmSet as a keyword parameter, and it works:

pro iimage, parm1, parm2, parm3, parm4, \$
IMAGE_LOCATION=imageLocation, \$
IMAGE_DIMENSIONS=imageDimensions, \$
RED_CHANNEL=redChannel, \$
GREEN_CHANNEL=greenChannel, \$
BLUE_CHANNEL=blueChannel, \$
ALPHA_CHANNEL=alphaChannel, \$
RGB_TABLE=rgbTable, \$
IDENTIFIER=IDENTIFIER, \$
oParmSet = oParmSet, \$
_EXTRA=_extra

IDL> a = dist(100)
IDL> ilmage, a, oParmSet=op, ident=id
IDL> b = dist(256)
IDL> data = op->Get(position=0)
IDL> r=data->setData(b)

Howver, I don't want to have to modify the iTools to pass back oParmSet. I think there must be a way to get this object reference from the identifier "id" that is passed back from the normal version of ilmage. Or alternatively set the data with the SetPropertyByldentifier on some object. Can anyone tell me how to do this? I've studied the manuals and can't figure it out.

Cheers,

Page 2 of 2 ---- Generated from comp.lang.idl-pvwave archive