Subject: Re: Default vector font size under X Posted by David Foster on Tue, 08 Apr 1997 07:00:00 GMT

View Forum Message <> Reply to Message

```
R. Bauer wrote:
>
> Liam Gumley wrote:
>>
>> Try typing the following commands right after starting IDL under X:
>>
>> print,!d.x_ch_size,!d.y_ch_size
>> window.0
>> print,!d.x_ch_size,!d.y_ch_size
>>
>> On an SGI, I get
>> 6 9, followed by 12 12.
>>
>> In other words, the default vector font size is changed to a
>> platform-specific value after the first window is created. Why this
>> happens is a mystery to me - RSI support just says that it happens.
>>
>
> I posted this problem a few mounth ago, we had the same results
> transfering source from PC to RS6000. Or from one RS6000 to another.
The following is the contents of an "idl_startup" script I use on
an SGI when porting code from a Sun (Solaris 2.X). Kind of the reverse
of your problem, but it illustrates some methods to use to solve
this kind of problem:
  ; Choose pseudo-color 8-bit visual
  device, pseudo_color=8
  ; Select default backing-store method to be provided by IDL, as SGI
  : X server does not seem to provide it
  device, retain=2
  ; Change size of font so programs fit on-screen (IRIX 4.0 or later)
  ; Reference: sgi.doc document in $IDL DIR/notes
  WIDGET CONTROL, $
    DEFAULT_FONT="-adobe-helvetica-bold-r-normal-*-14-100-*-*-*-* "
  ; Set default plotting font to same hardware font above
   (Create a pixmap window to avoid window creation upon
    calling DEVICE, FONT=; then delete window)
  window, xsize=5, ysize=5, /free, /pixmap
  !p.font = 0
               ; Use hardware font
```

device, FONT="-adobe-helvetica-bold-r-normal-*-10-100-*-*-*-*" ; Delete window created wdelete Hope someone finds this useful. Dave David S. Foster Univ. of California, San Diego Programmer/Analyst Brain Image Analysis Laboratory foster@bial1.ucsd.edu Department of Psychiatry 8950 Via La Jolla Drive, Suite 2200 (619) 622-5892 La Jolla, CA 92037 [UCSD Mail Code 0949]