
Subject: Bugs in UIS driver

Posted by [rivers](#) on Wed, 20 Mar 1991 05:18:35 GMT

[View Forum Message](#) <> [Reply to Message](#)

Judging from recent postings I think that developers from both RSI and Precision Visuals are reading this newsgroup. Thus I am posting some serious bug reports which I hope will lead to fixes ASAP.

There are several serious problems with the UIS driver under PV-WAVE versions 3.00 and 3.01. (UIS is the pre-DECWindows windowing system used under VMS. Many of us still use it since it gives satisfactory performance on the older, slower VAXstations, while DECWindows does not).

1) The mouse cursor disappears when it is moved into a PV-WAVE window. The fix to this bug is to type the command:

```
WAVE> DEVICE, CURSOR_ORIGINAL
```

However, this only makes the cursor visible in the the first PV-WAVE window. It will still be invisible in any subsequent windows created. To make it visible one must type the command DEVICE, CURSOR_ORIGINAL again.

2) The documentation is wrong concerning modifying the writing modes. The DEVICE keywords SET_IMAGE_MODE and SET_GRAPHICS_MODE are not implemented. However, the SET_GRAPHICS_FUNCTION keyword described under the X Windows driver IS supported. Table C.14 in the PV-WAVE User's Guide does NOT give the correct function codes for this device. The correct function codes are as follows (taken from SYS\$LIBRARY:UISUSRDEF.FOR)

```
PARAMETER UIS$C_MODE_TRAN = '00000001'X
PARAMETER UIS$C_MODE_COPY = '00000002'X
PARAMETER UIS$C_MODE_COMP = '00000003'X
PARAMETER UIS$C_MODE_COPYN = '00000004'X
PARAMETER UIS$C_MODE_OVER = '00000005'X
PARAMETER UIS$C_MODE_OVERN = '00000006'X
PARAMETER UIS$C_MODE_REPL = '00000007'X
PARAMETER UIS$C_MODE_REPLN = '00000008'X
PARAMETER UIS$C_MODE_ERAS = '00000009'X
PARAMETER UIS$C_MODE_ERASN = '0000000A'X
PARAMETER UIS$C_MODE_BIS = '0000000B'X
PARAMETER UIS$C_MODE_BIC = '0000000C'X
PARAMETER UIS$C_MODE_BISN = '0000000D'X
PARAMETER UIS$C_MODE_BICN = '0000000E'X
```

On our system I have set it up so that

```
WAVE> DEVICE, SET_GRAPHICS_FUNCTION=2
```

is executed during startup. This sets the graphics function to COPY mode, which

is what is generally desired (all bits are copied from the source to the destination).

3) The WPOSMENU routine does not work.

4) The TVMENU routine does not work.

5) None of the demonstration routines work. The logic in the demonstration package is set up so that it does not even attempt to run the workstation demos under the UIS driver.

Mark Rivers (516) 282-7708 or 5626
Building 815 rivers@bnlx26.nsls.bnl.gov (Internet)
Brookhaven National Laboratory rivers@bnl (Bitnet)
Upton, NY 11973 BNLX26::RIVERS (Physnet)
