
Subject: export to HDF

Posted by [Hassan](#) on Wed, 16 Jun 2010 10:26:43 GMT

[View Forum Message](#) <> [Reply to Message](#)

I have some data which is supplied in HDF data files compatible to HDF version 4.1r3. The HDF file contains: Annotations, RCI image and V Data-Gain settings and V data- Mode information. I opened the data (the RCI image) in ENVI and chose an ROI and now wonder how I can save it in HDF format with the same information as original data but new dimensions. I also want to change one of the variables in HDF format. I wonder if it's possible to do that in IDL or any other softwares. you may even know a reference about that which it'd be great if you send me the link so I can read how I can do that. I know there's `hdf_sd_create` in idl but think it's for creating new hdf file with new information.

Subject: Re: export to HDF

Posted by [Mariolncandenza](#) on Wed, 16 Jun 2010 19:19:12 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hassan,

The solution you will end up with will look a lot like creating a new HDF file, even if you populate it mostly with information from the parent file. If the file has many SDS, this can be rather tedious, but assuming you have a bunch of files to process, it's the way to go.

This is the call sequence for creating and populating an HDF. NOTE: This does NOT use `HDF_OPEN()` or `HDF_CLOSE`. It needs a better programmer than I to explain why, but this is complete sequence, the result of trial and error:

```
SDinterface_id = HDF_SD_START(<<outfile>>, /CREATE)
title=<<"TITLE OF NEW HDF FILE">>
HDF_SD_ATTRSET, SDinterface_id, 'TITLE',title
; create SDS in HDF file
for isds=0,nsds-1 do begin
    SDdataset_id =
HDF_SD_CREATE(SDinterface_id,<<SDS_NAME>>,<<SDS_DIMS>>,hdf_type=
<<datatypes_idl2hdf[SDS_TYPE]>>)
    HDF_SD_ADDDATA,SDdataset_id,<<SDS_DATA>>
    HDF_SD_ENDACCESS, SDdataset_id
endfor
;; shut it down
HDF_SD_END, SDinterface_id
```

You will need, for each SDS:

```
SDS_NAME
SDS_DIMS = SIZE(SDS,/DIM)
SDS_TYPE = DATATYPES_IDL2HDF[SIZE(SDS,/TYPE)]; see NOTE
SDS_DATA
```

NOTE: This array converts between the output of SIZE and the data type codes used by the HDF interface. See the help for more details:

```
DATATYPES_IDL2HDF=[-1,21,22,24,5,6,-1,-1,-1,-1,-1,-1,23,25,2 6,27]
```

Hope this helps,

--Edward H.

Subject: Re: export to HDF
Posted by [Hassan](#) on Wed, 16 Jun 2010 22:12:44 GMT
[View Forum Message](#) <> [Reply to Message](#)

Thanks for the information. It seems to me we are crating a new HDF file and writing new attributes to them that it is different with what I need which is keeping the attributes from original one and changing the dimension part or copying the arribute from original file into new file and adding new dimensions. or I may misunderstood it since Im not familar with HDF files.
