Subject: Error when calling ENVI_WRITE_ENVI_FILE Posted by Simon Mitchell on Fri, 25 Oct 2013 15:35:13 GMT

View Forum Message <> Reply to Message

Hi All,

I am getting an error when using the ENVI_WRITE_ENVI_FILE command. Note that I am a beginner with using IDL.

The error that I am getting is:

ERROR: "FLOAT: Struct expression not allowed in this context: DATA." The result may be invalid.

I have to add, that this error does not stop my code from creating a file, but the values are not what I am expecting.

A little background on what I am trying to do.

I want to be able to replicate in IDL (for batch script) opening multiple ASCII files (each representing a band of image data) and then saving them as an ENVI Standard file with multiple bands.

So essentially doing the "File->Open External File->Generic Formats->ASCII" for three files, then "Save File As->ENVI Standard" as one file with three bands in BSQ format.

My code is as follows, and I am just using a dummy test image of 11 samples and lines as my input, with 6 header lines.

```
PRO COMBINE_ASCII
opendir = 'D:\Directory'
redfile = opendir+'red_output_short.txt'
mirfile = opendir+'mir template short.txt'
tirfile = opendir+'tir template short.txt'
ofname = opendir+'random_image_1'
descrip = 'Random point image #1'
ns = 11
nl = 11
nc = 3*nl
rnd_data = FLTARR([ns], [nc]); float array of ns = 11, nl = 11 for 3 bands
;rnd data = FLTARR([ns],[nl],3)
Open the files
OPENR, lun_red, redfile, /GET_LUN
red_data = READ_ASCII(redfile, DATA_START = 6, DELIMITER = string(9B))
rnd data = [red data]
```

```
OPENR, lun mir, mirfile, /GET LUN
mir_data = READ_ASCII(mirfile, DATA_START = 6, DELIMITER = string(9B))
rnd_data = [[rnd_data], [mir_data]]
OPENR, lun_tir, tirfile, /GET_LUN
tir_data = READ_ASCII(tirfile, DATA_START = 6, DELIMITER = string(9B))
rnd data = [[rnd data], [tir data]]
;rnd_data = [[red_data],[mir_data],[tir_data]]
;OPENW, lun_out, ofname, /GET_LUN
print, rnd_data
:reddata = READ ASCII(redfile, DATA START = 6)
;mirdata = READ ASCII(mirfile, DATA START = 6)
;tirdata = READ ASCII(tirfile, DATA START = 6)
ENVI WRITE ENVI FILE, rnd data, FILE TYPE = 4, INTERLEAVE = 0, NB = 3, NS = ns, NL =
nl, OUT_DT = 4, OUT_NAME = ofname
; FILE_TYPE = 4
  ENVI_SETUP_HEAD, FNAME = ofname, NS = ns, NL = nl, NB = 3, $
     XSTART = 0, YSTART = 0, DATA TYPE = 1, INTERLEAVE = 0, $
     file type = 4, $
     DESCRIP = descrip, /WRITE, /OPEN
CLOSE, /ALL
```

END

I am wondering if any one can tell me where I am going wrong, or could suggest a better way of doing this!!! As you can probably guess, I am not the best idl coder and have only been using it for a short time, but I think I may be doing something wrong with the array concatenation.

Many thanks in advance for your help.

Simon

Subject: Re: Error when calling ENVI_WRITE_ENVI_FILE Posted by Phillip Bitzer on Fri, 25 Oct 2013 16:02:40 GMT View Forum Message <> Reply to Message

Hi Simon-

Well, you're not getting what you think in the "data" variables. Check out this from the help for READ_ASCII:

The result is an IDL structure array containing the data

And this variable (ultimately) is what you're using in ENVI_WRITE_ENVI_FILE. Only problem is, according to the help, the parameter that you should pass is:

This is a 2D or 3D data array of type byte, integer, unsigned integer, long integer, unsigned long integer, long 64-bit integer, unsigned long 64-bit integer, floating-point, double-precision, complex, or double-precision complex.

You have to extract the pertinent data from the READ_ASCII function, and put it in the format ENVI_WRITE_ENVI_FILE expects. (I'll note there's probably better ways than using READ_ASCII here, but you can certainly get it to work.)

There's a couple of other things going on. Consider these lines:

```
rnd_data = FLTARR([ns], [nc]) ;float array of ns = 11, nl = 11 for 3 bands
...
red_data = READ_ASCII(redfile, DATA_START = 6, DELIMITER = string(9B))
rnd_data = [red_data]
```

Basically, the first line isn't doing anything for you, because you change the variable (more formally, dynamically cast the variable) from an array to a structure in the last line.

Hope this helps!

Subject: Re: Error when calling ENVI_WRITE_ENVI_FILE Posted by Josh Sixsmith on Fri, 25 Oct 2013 21:57:19 GMT

View Forum Message <> Reply to Message

```
> OPENR, lun_red, redfile, /GET_LUN
> red_data = READ_ASCII(redfile, DATA_START = 6, DELIMITER = string(9B))
```

The READ_ASCII function doesn't need the file to be opened using openr. READ_ASCII will handle that itself. Just pass it the string containing the filename of the ascii file to read.

Use the openr command in conjunction with the read/readf/readu commands.

Cheers Josh

Subject: Re: Error when calling ENVI_WRITE_ENVI_FILE Posted by Simon Mitchell on Mon, 28 Oct 2013 15:55:03 GMT

View Forum Message <> Reply to Message

```
Thanks for responding Phil and Josh.
```

```
I guess I'm just not understanding what is going on here.
What is the difference between a structure array and a data array?
When I use the code
red_data = READ_ASCII(redfile, DATA_START = 6, DELIMITER = string(9B))
rnd data = [red data]
print, red_data
print, rnd_data
I get the result (using a 3x3 image as an example)
111
111
111
111
111
111
}
I then want to add the second band to the data (to make it BSQ format)
mir data = READ ASCII(mirfile, DATA START = 6, DELIMITER = string(9B))
rnd_data = [[rnd_data], [mir_data]]
print, rnd_data
I get
111
111
111
}{
222
222
222
when what I would expect would be
{
111
111
111
222
222
```

222

and so on for the third band. Am I correct in my assumption? I assume that what I'm actually getting is a [3,3,3] array, rather than my expected [3,9] array.

But I'm also not understanding is why the ENVI_WRITE_ENVI_FILE is not accepting this data? Would you please be able to step me through my questions?

Or if someone has a better method for loading ASCII files into an ENVI standard image, could they please pass this on to me.

Many thanks in advance

Simon

Subject: Re: Error when calling ENVI_WRITE_ENVI_FILE Posted by Phillip Bitzer on Mon, 28 Oct 2013 16:34:13 GMT View Forum Message <> Reply to Message

Hi Simon-

First, some terminology. You can have an "array of structures". You can also have a "structure with tags that are arrays".

Before we jump into it, the use of help is much more, well, helpful, than print. You'll see this in action below.

Consider this variable:

 $IDL > str = {data: FLTARR(3, 3)}$

Notice "str" is a structure, and "data" is a tag (or field) of "str". Try this:

IDL> help, str

So, "str" is in fact a structure. In order to access the tag data, we use:

IDL> help, str.data

So, str.data (again, the tag "data" in the structure "str") is a 3x3 float array.

Print it if you'd like: IDL> print, str.data

This is how you deal with a "structure that has tags that are arrays".

We can take this further. Consider:
arrOfStr = REPLICATE(str, 2)

Now, 'arrofStr' is an "array of structures". See for yourself:
IDL> help, arrOfStr

You can print this too:
IDL> print, arrOfStr

What you *really* want is the data tag from each structure:
IDL> help, arrOfStr.data
IDL> print, arrOfStr.data

Subject: Re: Error when calling ENVI_WRITE_ENVI_FILE Posted by Josh Sixsmith on Tue, 29 Oct 2013 01:07:37 GMT View Forum Message <> Reply to Message

> What you *really* want is the data tag from each structure:
> IDL> help, arrOfStr.data
> IDL> print, arrOfStr.data
> ------

Exactly what Phillip has mentioned. Use the tag names to get at the actual data array contained within the structure. The "data" argument to "ENVI_WRITE_ENVI_FILE" is the array itself, not a structure that contains the arrays.

You could pre-allocate an array that will contain all the bands.

eg

```
red_data = READ_ASCII(redfile, DATA_START = 6, DELIMITER = string(9B))
columns = 4000 ; or whatever it may be
rows = 4000
bands = 7
all_bands = FLTARR(columns, rows, bands)
all_bands[*,*,0] = red_data.data_tag_name ;data_tag_name could be data as in the example provided by Phillip.
```

and so on for all the necessary bands.

bnames=['1','2','3','4','5','6','7']

Then

ENVI_WRITE_ENVI_FILE, all_bands, bnames=bnames, nb=bands, nl=rows, ns=columns, out_name='my_envi_file'

Hope that helps.

Cheers Josh

Subject: Re: Error when calling ENVI_WRITE_ENVI_FILE Posted by Simon Mitchell on Fri, 01 Nov 2013 11:17:58 GMT View Forum Message <> Reply to Message

Thank you for all your help Phil and Josh.

My code is working and I am getting good results, and I have learnt some more about IDL.

Thank you