Subject: Re: Limiting the number of VM instances Posted by robert.dimeo on Thu, 22 Jan 2004 22:46:11 GMT

View Forum Message <> Reply to Message

David Fanning <david@dfanning.com> wrote in message news:<MPG.1a79a4c18d88cf949897ac@news.frii.com>... > Rob Dimeo writes:

- >> Once again the helpful folks at RSI suggested a solution
- >> and I wrote a function encapsulating the logic called
- >> LIMIT_VM_INSTANCE. The main idea is to use a shared memory segment.

- > Wow, that looks very much like a singleton object (without
- common blocks), doesn't it. :-)

> Cheers,

- > David
- Hi. The version of the function below now eliminates the need for passing in a name. It is more of a "node-specific" singleton (pointed out to me by RSI). It uses the CALLS keyword to HELP to get the routine information out and create a memory segment name unique to the routine in which LIMIT VM INSTANCE is being called. Thanks again to RSI for the tip!

NAME:

LIMIT_VM_INSTANCE

PURPOSE:

Function that prevents more than one instance of an individual application from running in the IDL VM.

In your widget application your first program statement in the widget definition module should be RET = LIMIT VM INSTANCE(/INIT). If the return value is 0 then there is a process already running and you should exit/return from the code. In the cleanup routine for your application you should put in the following statement: RET = LIMIT_VM_INSTANCE(/EXIT)

Basic logic for this function credited to Jim Pendleton at Research Systems.

INPUT PARAMETERS:

: NONE **INPUT KEYWORDS:** INIT: Set this keyword prior to creating widgets in the application. EXIT: Set this keyword in the widget cleanup routine. COMMON BLOCKS: NONE **REQUIREMENTS:** IDL 6.0 or higher to run in the Virtual Machine **RESTRICTIONS:** NONE **AUTHOR:** Robert M. Dimeo, Ph.D. NIST Center for Neutron Research 100 Bureau Drive Gaithersburg, MD 20899 Phone: (301) 975-8135 E-mail: robert.dimeo@nist.gov http://www.ncnr.nist.gov/staff/dimeo CATEGORY: Widget applications, application distribution with VM **CALLING SEQUENCE:** IDL> RET = LIMIT_VM_INSTANCE(INIT = init, EXIT = exit) **EXAMPLE:** Consult the code appended to this function named SHARED EXAMPLE for typical usage. Compile everything in this module and then run SHARED_EXAMPLE. **MODIFICATION HISTORY:** 01-22-04 (RMD): Initial program written

......

```
function limit_vm_instance, INIT = init,
                  EXIT = exit
help, calls = calls
diff = Imgr(/vm) ? 3 : 2
segment_name = (strsplit(calls[n_elements(calls) - diff], ' ', $
        /extract))[0]
if keyword_set(init) then begin
 if Imgr(/vm) then begin
   os handle = 'mysegment'+' '+segment name
   shmmap, segment_name, template = [0B], $
     os handle = os handle
   v = shmvar(segment_name)
   if (v[0] eq 1) then begin
     msg = 'An instance of this code is already running.'
     v = dialog_message(msg, /error)
     shmunmap,segment_name
     return,0
   endif
   v[0] = 1
 endif
 return,1
endif
if keyword_set(exit) then begin
 if Imgr(/vm) then shmunmap, segment_name
 return,1
endif
return,1
end
: EXAMPLE WIDGET CODE FOLLOWS
pro shared_example_cleanup,tlb
; Call the function that limits the number of VM instances
; with the EXIT keyword set.
ret = limit vm instance(/exit)
end
pro shared_example_event,event
uname = widget info(event.id,/uname)
case strupcase(uname) of
'QUIT': widget_control,event.top,/destroy
else:
endcase
pro shared example
; Call the function that limits the number of VM instances
```

```
; with the INIT keyword set. Note that we also will need to
call this same function with the EXIT keyword set in a
 cleanup routine...this is necessary to unmap the variable that
; is in shared memory. We need a unique process name for
; the memory segment so we can just use the name with which
; we'll register the application with the XMANAGER.
register name = 'shared example'
ret = limit_vm_instance(/init)
if not ret then return
; The following simple widget code just puts up a QUIT button.
tlb = widget base(title = 'shared memory example', $
 /tlb_frame_attr,/col)
void = widget_button(tlb,value = 'quit',xsize = 200, $
 uname = 'quit')
widget_control,tlb,/realize
; We must use a cleanup routine in order to unmap the variable
; from shared memory so specify it here. Remember to use the
; register name variable here.
xmanager,register name,tlb,/no block, $
 cleanup = 'shared example cleanup', $
 event_handler = 'shared_example_event'
end
```