Subject: Re: how to composite a mapcoord object using geographic coordinate(no projection)

Posted by Yngvar Larsen on Tue, 25 Feb 2014 09:25:30 GMT

View Forum Message <> Reply to Message

On Tuesday, 25 February 2014 00:48:48 UTC+1, David Fanning wrote:

- > Fabien writes:
- >
- >
- >> I believe that these are also "standard" formats but less transparent.

These files are indeed TIFF 6.0 conformant, but the information in them do not contain enough GeoTIFF tags to have a uniquely defined grid without external information. Thus, you need ugly special cases in your GeoTIFF reader to handle this. Or a specific reader for each. I did the latter for SRTM tiles, which only contain "ModelPixelScaleTag" and "ModelTiepointTag", but no info on the coordinate system.

- > I don't know. I've seen three files in the past three days that purport
- > to be "GeoTiff" files, and not a one of them appears to have been
- > written by someone who read the TIFF definitions and standards document.

You should not confuse GeoTIFF with TIFF. A conformant TIFF file can contain almost any imaginable tags/metadata (or not...). However, such extra information can be ignored a conformant TIFF _reader_. GeoTIFF is such extra information.

 $GCS_WGS_84 = 4326$

> Can you just make it up and call it a GeoTiff?

I guess you can use at least one of the defined GeoTIFF tags, and call it a GeoTIFF file. But if you would like your file to be self contained, I would say you should at least follow the cookbooks in the spec:

http://www.remotesensing.org/geotiff/spec/geotiff2.6.html#2. 6.3 http://www.remotesensing.org/geotiff/spec/geotiff2.7.html#2. 7.3

Specifically, for the geographic coordinate systems discussed in this thread, you should do the following

case GEOGRAPHIC: Check the list of standard GCS's and use the corresponding code. To use a code both the Datum, Prime Meridian, and angular units must match those of the code.

Store in: GeographicTypeGeoKey and skip to Step 4. If none of the coded GCS's match exactly, then this is a user-defined GCS. Check the list of standard datums,

Prime Meridians, and angular units to define your system. Store in: GeogGeodeticDatumGeoKey, GeogAngularUnitsGeoKey, GeogPrimeMeridianGeoKey and skip to Step 4.

If none of the datums match your system, you have a user-defined datum, which is an odd system, indeed. Use the GeogEllipsoidGeoKey to select the appropriate ellipsoid or use the GeogSemiMajorAxisGeoKey, GeogInvFlatteningGeoKey to define, and give a reference using the GeogCitationGeoKey. Store in: GeogEllipsoidGeoKey, etc. and go to Step 4.

The file that J. Zhou sent you contain the following information on the coordinate system:

GEOGRAPHICTYPEGEOKEY

INT 4326

GEOGANGULARUNITSGEOKEY

INT 9102

which means a standard GCS (WGS-84) and angular units (degrees) plus

GTMODELTYPEGEOKEY

INT

GTRASTERTYPEGEOKEY

INT 1

which means Geographical coordinate system with "PixellsArea". Thus, this is a well defined self contained GeoTIFF file as far as I understand. On the other hand, the SRTM tile I sent you did not contain any of this, and needs special treatment with external information.

Yngvar