

---

Subject: Persistent Object Graphics Not Persistent in Resizeable Windows

Posted by [davidf](#) on Fri, 06 Jun 1997 07:00:00 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Folks,

I've run into a problem in which I lose all my axes labeling if I resize my draw widget object window before evoking the Draw method of the window. Here is a bug report and some sample code to see the problem. (Those of you who want to see how to add axes to a surface plot, take note. :-))

Cheers,

David

\*\*\*\*\*

Name: David Fanning

E-mail Address: [davidf@dfanning.com](mailto:davidf@dfanning.com)

IDL version: { x86 Win32 Windows 5.0 Apr 28 1997}

Platform and OS: WindowsNT 4.0, Service Pack 1

Description of Problem: -----

"Persistent" object graphics are not very persistent if you resize the object window before you evoke the Draw method. Here I am losing the axes labeling when the window is resized.

Example Code: -----

Pro XSurface\_Cleanup, tlb

; Come here when program dies. Free all created objects.

Widget\_Control, tlb, Get\_UValue=info

Obj\_Destroy, info.thisContainer

END

;-----

PRO XSurface\_Resize, event

; The only events generated by this simple program are resize  
; events, which are handled here.

; Get the info structure.

Widget\_Control, event.top, Get\_UValue=info, /No\_Copy

; Resize the draw widget.

;88

; Here is the problem. Comment this line out and uncomment the

; two below it to see that the problem comes from resizing the

; window.

info.thisWindow->SetProperty, Dimension=

;info.thisWindow->erase, Color=

;Wait, 1

;88

; Redisplay the graphic.

info.thisWindow->Draw, info.thisView

;Put the info structure back.

Widget\_Control, event.top, Set\_UValue=info, /No\_Copy

END

-----

PRO XSurface, data

; Need some data.

Catch, error

IF error NE 0 THEN BEGIN ; Can't find LoadData.

  data = DIST(40)

  GOTO, CreateView

ENDIF

IF N\_Parms() EQ 0 THEN data = LoadData(2)

CreateView:

Catch, /Cancel

; Create a view. Use RGB color. Charcoal background.

; The viewplane rectangle extends from -1 to 1 in XY directions.

thisView = OBJ\_NEW('IDLgrView', Color=, Viewplane\_Rect=)

; Create a model and add it to the view.

```

thisModel = OBJ_NEW('IDLgrModel')
thisView->Add, thisModel

; Create a wire mesh surface. Make it yellow.

thisSurface = OBJ_NEW('IDLgrSurface', data, Color=)

; Create axes for the surface. Color them green.

xAxis = Obj_New("IDLgrAxis", 0, color=, Ticklen=0.1)
yAxis = Obj_New("IDLgrAxis", 1, color=, Ticklen=0.1)
zAxis = Obj_New("IDLgrAxis", 2, color=, Ticklen=0.1)

; Add the surface and axes to the model.

thisModel->Add, thisSurface
thisModel->Add, xAxis
thisModel->Add, yAxis
thisModel->Add, zAxis

; Get the data ranges for the surface.

thisSurface->GetProperty,XRange=xrange,YRange=yrange,ZRange=zrange

; Set the range and location of the axes. In this case,
; we are scaling the data into -0.5 to 0.5, so that even
; when the surface is rotated, it stays inside the -1 to 1
; viewing rectangle. Note that not all values in the Location
; keyword are used. (I've put really large values into the
; positions that are not being used to demonstrate this.) For
; example, with the X axis only the Y and Z locations are used.

xAxis->SetProperty, Range=xrange, Location=
yAxis->SetProperty, Range=yrange, Location=
zAxis->SetProperty, Range=zrange, Location=

; Scale the surface and axes into the range -0.5 to 0.5.

xs = [-0.5, 1/(xrange-xrange)]
ys = [-0.5, 1/(yrange-yrange)]
zs = [-0.5, 1/(zrange-zrange)]
thisSurface-> SetProperty,XCoord_Conv=xs, YCoord_Conv=ys, ZCoord_Conv=zs
xAxis-> SetProperty, XCoord_Conv=xs
yAxis-> SetProperty, YCoord_Conv=ys
zAxis-> SetProperty, ZCoord_Conv=zs

; Rotate model to the standard view.

```

```
thisModel->Rotate,, -90 ; To get the Z-axis vertical.  
thisModel->Rotate,, 30 ; Rotate it slightly to the right.  
thisModel->Rotate,[1,0,0], 30 ; Rotate it down slightly.
```

;Create the widgets to view the surface.

```
tlb = Widget_Base(Title='Surface Example', Column=1, TLB_Size_Events=1)  
drawID = Widget_Draw(tlb, XSize=300, YSize=300, Graphics_Level=2,  
Retain=2)  
Widget_Control, tlb, /Realize
```

; Get the window destination object.

```
Widget_Control, drawID, Get_Value=thisWindow
```

; Draw the view in the window.

```
thisWindow->Draw, thisView
```

```
; Create a container object to hold all the other  
; objects. This will make it easy to free all the  
; objects when we are finished with the program.
```

```
thisContainer = Obj_New('IDLgrContainer')
```

; Add the view to the container.

```
thisContainer->Add, thisView
```

; Create an INFO structure to hold needed program information.

```
info = { thisContainer:thisContainer, $ ; The object container.  
        thisWindow:thisWindow, $ ; The destination window  
        object.  
        thisView:thisView } ; The view object.
```

; Store the info structure in the UValue of the TLB.

```
Widget_Control, tlb, Set_UValue=info, /No_Copy
```

; Call XManager. Set a cleanup routine so the objects  
; can be freed upon exit from this program.

```
XManager, 'xsurface', tlb, Cleanup='XSurface_Cleanup', /No_Block, $  
Event_Handler='XSurface_Resize'
```

```
END
```

```
-----
```

Known Workarounds or Fixes: -----

Don't resize windows or store all object components in the info structure so the object can be re-built each time.

[RSI Technical Support Response: -----

Pending.

--

David Fanning, Ph.D.  
Fanning Software Consulting  
Customizable IDL Programming Courses  
Phone: 970-221-0438 E-Mail: [davidf@dfanning.com](mailto:davidf@dfanning.com)  
Coyote's Guide to IDL Programming: <http://www.dfanning.com>  
IDL 5 Reports: <http://www.dfanning.com/documents/anomaly5.html>

---