
Subject: Re: GUI procedure to function
Posted by [R.Bauer](#) on Wed, 07 Apr 2004 13:30:41 GMT
[View Forum Message](#) <> [Reply to Message](#)

Nitin Katiyar wrote:

> Hi.
> I wish to convert a GUI procedure writtern in IDL ,to its equivalent
> function so that I am
> able to return values back to the calling procedure. Since the
> procedure doesnt return the values , I need the function to do the
> same.
>
> I am posting the procedure listing along with this mail.Kindly someone
> please
> tell me the way to convert it to a correspondidng function so that I
> can return
> the input variable back to calling procedure.
>
> TIA
> -shishir

Hi

you have to declare the procedure wid_input as function.
The return statement must be behind the XMANAGER.

The return value must be defined outside of the GET_UVALUE structure of
the base, because this is destroyed at the moment the XMANAGER is killed.

I prefer pointer, here is a small example

PRO wid5_event,event

WIDGET_CONTROL,event.top,GET_UVALUE=x

cmd=WIDGET_INFO(event.id,/UNAME)

CASE cmd OF

'QUIT' : WIDGET_CONTROL,event.top,/DESTROY

'PRINT': BEGIN

id=WIDGET_INFO(event.top,FIND_BY_UNAME='TEXT')

WIDGET_CONTROL,id,SET_VALUE=(*x).value

(*x).value='Goodby'

END

```
ELSE:
ENDCASE
```

```
END
```

```
function wid5
  x={value:'Hello'}
  x=PTR_NEW(x,/NO_COPY)

  id_base=WIDGET_BASE(ROW=3)
  id_PRINT=WIDGET_BUTTON(id_base,VALUE='PRINT',UNAME='PRINT')
  id_quit=WIDGET_BUTTON(id_base,VALUE='QUIT',UNAME='QUIT')
  id_text=WIDGET_TEXT(id_base,VALUE='',UNAME='TEXT')

  WIDGET_CONTROL,id_base,/REALIZE,SET_UVALUE=x
  XMANAGER,'wid5',id_base
  result=*x
  ptr_free,x
  return,result
END
```

regards

Reimar

```
>
>
> *-----Listing of wid_input.pro-----*
>
> pro wid_input_event, ev
> WIDGET_CONTROL, ev.id, GET_VALUE=input
> if(input eq 'OK') then $
> WIDGET_CONTROL, ev.top, /DESTROY $
> else if(input eq 'Cancel') then $
> Result = DIALOG_MESSAGE('You have not entered the Discharge Value',
> /INFORMATION, $
> TITLE='Warning')$
> else WIDGET_CONTROL, ev.id, SET_VALUE=""
> end
>
> pro wid_input,type ;basically type is passed as a parameter to this
> procedure
> type='injection' ;here i have taken a default value to run it alone.
> ;type='pumping'
```

```

>
> case type of
> 'pumping':begin
>   base = WIDGET_BASE(XOFFSET=5 ,YOFFSET=5 ,SCR_XSIZE=180 ,SCR_YSIZE=100
>   $
>   ,TITLE='Discharge Input' ,SPACE=3 ,XPAD=3 ,YPAD=3
>   ,TLB_FRAME_ATTR=1)
>   field = CW_FIELD(base, TITLE = "Enter the Discharge Value",
>   /FRAME,/RETURN_EVENTS,XSIZE=4)
>   button1 = WIDGET_BUTTON(base, VALUE='OK', UVALUE='Ok',XOFFSET=20
>   ,YOFFSET=40 ,SCR_XSIZE=60 $
>   ,SCR_YSIZE=20,/ALIGN_CENTER)
>   button2 = WIDGET_BUTTON(base, VALUE='Cancel',
>   UVALUE='CANCEL',XOFFSET=90 ,YOFFSET=40 $
>   ,SCR_XSIZE=60 ,SCR_YSIZE=20,/ALIGN_CENTER)
>   end
> 'injection':begin
>   base = WIDGET_BASE(XOFFSET=5 ,YOFFSET=5 ,SCR_XSIZE=320 ,SCR_YSIZE=140
>   $
>   ,TITLE='Injection Well Input' ,SPACE=3 ,XPAD=3 ,YPAD=3
>   ,TLB_FRAME_ATTR=1,/COLUMN)
>   field1 = CW_FIELD(base, TITLE = "Enter the Discharge Value",
>   /FRAME,/RETURN_EVENTS,XSIZE=4)
>   field2 = CW_FIELD(base, TITLE = "Enter the Concentration Value",
>   /FRAME,/RETURN_EVENTS,XSIZE=4)
>   Bbase = WIDGET_BASE(base,XOFFSET=5 ,YOFFSET=80 ,SCR_XSIZE=320
>   ,SCR_YSIZE=30 $
>   ,SPACE=3 ,XPAD=3 ,YPAD=3 ,TLB_FRAME_ATTR=1)
>   button1 = WIDGET_BUTTON(Bbase, VALUE='OK', UVALUE='Ok',XOFFSET=70
>   ,YOFFSET=5 ,SCR_XSIZE=60 $
>   ,SCR_YSIZE=20,/ALIGN_CENTER)
>   button2 = WIDGET_BUTTON(Bbase, VALUE='Cancel',
>   UVALUE='CANCEL',XOFFSET=140 ,YOFFSET=5 $
>   ,SCR_XSIZE=60 ,SCR_YSIZE=20,/ALIGN_CENTER)
>   end
> ENDCASE
> WIDGET_CONTROL, base, SET_UVALUE=field
> ;WIDGET_CONTROL, field, SET_VALUE=""
> WIDGET_CONTROL, base, /REALIZE
> XMANAGER, 'wid_input', base,/JUST_REG
> end

```

--

Reimar Bauer

Institut fuer Stratosphaerische Chemie (ICG-I)
Forschungszentrum Juelich

email: R.Bauer@fz-juelich.de

a IDL library at ForschungsZentrum Juelich

http://www.fz-juelich.de/icg/icg-i/idl_icglib/idl_lib_intro.html

=====