
Subject: reading binary file with READ_BINARY
Posted by [mishooax](#) on Thu, 17 Oct 2013 12:00:10 GMT
[View Forum Message](#) <> [Reply to Message](#)

Folks,

I am trying to read a binary file in IDL containing a simple 2D array of 360x180 values. For reference, the binary file can be found here:

<http://transcom.project.asu.edu/download/transcom03/smoothmap.fix.2.bin>

Here is what the readme for this .bin says:

The file 'smoothmap.fix.2.bin' contains a single real, binary array dimensioned 360 x 180. The array contains the numbers 1 through 22, denoting each of the 22 basis functions in the TransCom 3 experiment. This file was written on an SGI Origin 2000 hosting UNIX.

And my code:

```
GET_LUN, fstart  
OPENR, fstart, FFilename
```

```
mask_data = READ_BINARY(fstart, DATA_DIMS=[360,180], DATA_TYPE=4) ; float data
```

Now mask_data contains only junk values:

```
print, mask_data[0:100] gives  
-2.24089e-038  0.000000  0.000000  0.000000  ....
```

Why would that be?

Also, I've noticed the .bin file size is 259208 bytes, aka 8 bytes more than the space required to store a 360x180 float array. I've been looking at this for an hour now and I'm stumped. Played around with endian-ness settings but that did not help.

How can I read in this file correctly?

Thank you!
