
Subject: Re: peeling away layers

Posted by [lance.luvaul](#) on Wed, 14 Aug 2013 12:52:06 GMT

[View Forum Message](#) <> [Reply to Message](#)

On Wednesday, August 14, 2013 6:51:29 PM UTC+10, lance....@gmail.com wrote:

> On Friday, August 9, 2013 6:41:46 PM UTC+10, lance....@gmail.com wrote:

>

>> How do I gain access to the idlitvissurface object underlying a "New Graphics" surface object (created using the surface() function)?

>

>>

>

>>

>

>>

>

>> I need to programmatically set the scale_vertex_color array, which I cannot seem to do with the surface objref but can with the idlitvissurface objref like so: "my_idlitvissurface->setproperty, scale_vertex_color=[...]"

>

>>

>

>>

>

>>

>

>> Thanks in advance,

>

>>

>

>> Lance

>

>

>

> Finally figured out how to do this. After you've instantiated your NG surface object (and assuming it's the only one), you can set the scale_vertex_color property this way:

>

>

>

> igetproperty, 'surface', scale_vertex_color=svc

>

> svc[3] = clip

>

> isetproperty, 'surface', scale_vertex_color=svc

>

>

>

> The first arg to i(g)s etproperty is a path-like string that qualifies the itools visualization object. If

'surface' isn't unique enough, I believe you can use igetid() somehow immediately after instantiating the NG surface to get the fully qualified string (looks something like: "/TOOLS/GRAPHIC/WINDOW/VIEW_1/VISUALIZATION LAYER/DATA SPACE/SURFACE").

>

>

>

> Hope this helps someone else...

Here's another way to do it:

```
oSystem = _IDLitSys_GetSystem()
```

```
oVis = oSystem->IDLitContainer::GetByIdentifier(igetid('surface'))
```

```
ovis->getproperty, scale_vertex_color=svc
```

```
svc[3] = clip
```

```
ovis->setproperty, scale_vertex_color=svc
```
