
Subject: Re: IDLgrAxis object with /LOG keyword
Posted by [davidf](#) on Thu, 18 Jan 2001 19:14:49 GMT
[View Forum Message](#) <> [Reply to Message](#)

Marc Schellens (m_schellens@hotmail.com) writes:

- > I want to create a logarithmic plot with object graphics.
- > So I thought I just set the /LOG keyword to the IDLgrAxis object and
- > scale the data accordingly.
- > But with the /LOG keyword the Axis is drawn on a different location.
- > Does anybody have an example how to do it right?

Humm. This gave me some trouble too. Then I remembered that CRANGE returns the log of the range when axes are set to log type. So, to get things to work, I had to scale the axis (Z-Axis in this case) differently from the data in the Z direction.

Here is how I modified my FSC_SURFACE program to get it to work with a log Z axis. (I set the LOG keyword on the IDLgrAxis command for the Z axis.)

```
; The axes may not use exact axis scaling, so the ranges may
; have changed from what they were originally set to. Get
; and update the range variables.
```

```
xAxis->GetProperty, CRange=xrange
yAxis->GetProperty, CRange=yrange
zAxis->GetProperty, CRange=zrange
zrange_surf = [10^zrange[0], 10^zrange[1]]
```

```
; Set scaling parameters for the surface and axes so that everything
; is scaled into the range -0.5 to 0.5. We do this so that when the
; surface is rotated we don't have to worry about translations. In
; other words, the rotations occur about the point (0,0,0).
```

```
xs = Normalize(xrange, Position=[-0.5,0.5])
ys = Normalize(yrange, Position=[-0.5,0.5])
zs = Normalize(zrange, Position=[-0.5,0.5])
zsurf = Normalize(zrange_surf, Position=[-0.5,0.5])
```

```
; Scale the axes and place them in the coordinate space.
; Note that not all values in the Location keyword are
; used. (I've put really large values into the positions
; that are not being used to demonstrate this.) For
; example, with the X axis only the Y and Z locations are used.
```

```
xAxis->SetProperty, Location=[9999.0, -0.5, -0.5], XCoord_Conv=xs
yAxis->SetProperty, Location=[-0.5, 9999.0, -0.5], YCoord_Conv=ys
zAxis->SetProperty, Location=[-0.5, 0.5, 9999.0], ZCoord_Conv=zs
```

; Scale the surface.

```
thisSurface->SetProperty, XCoord_Conv=xs, YCoord_Conv=ys, ZCoord_Conv=zsrf
*****
```

I put this example program here if you want to try it out:

ftp://ftp.dfanning.com/oub/outgoing/misc/fsc_surface_log.pro

I ran it like this:

```
IDL> .Compile fsc_surface_log
IDL> fsc_surface, dist(50)*40 > 1
```

Cheers,

David

--

David Fanning, Ph.D.

Fanning Software Consulting

Phone: 970-221-0438 E-Mail: davidf@dfanning.com

Coyote's Guide to IDL Programming: <http://www.dfanning.com/>

Toll-Free IDL Book Orders: 1-888-461-0155

Subject: Re: IDLgrAxis object with /LOG keyword

Posted by [marc schellens\[1\]](#) on Fri, 19 Jan 2001 06:53:21 GMT

[View Forum Message](#) <> [Reply to Message](#)

Thanks alot, looking for [XY]RANGE was the right hint.

:~))) marc
