
Subject: log scale of data coloring of IDLgrVolume object, not the axes

Posted by [tbowers0](#) on Tue, 29 Jan 2002 22:03:35 GMT

[View Forum Message](#) <> [Reply to Message](#)

Ok, I think I've figured out the whole log axis thing to get an IDLgrSurface axis to show log scale, its all about scaling the xyzCoord_Conv property of the surface with the logged bounds of your data.

But, I'm having trouble carrying this over using log scale for the coloring of an IDLgrVolume object and the associated Hcolorbar from David F. (keeping the xyz axes linear, just logging the color ramp).

Could anyone help?

thanks

Subject: Re: log scale of data coloring of IDLgrVolume object, not the axes

Posted by [tbowers0](#) on Sat, 09 Feb 2002 02:26:36 GMT

[View Forum Message](#) <> [Reply to Message](#)

"1" <j@msn.com> wrote in message news:<a40v84\$h4k\$1@ra.nrl.navy.mil>...

> David Fanning <david@dfanning.com> wrote in message

>>

>> HColorbar isn't designed for log scales, of course,

>> but I think it is just a matter of passing it a

Ahhh, but it can! (with some foolin' around) After much ballyhooing with the LOG keyword to the textAxis in Hcolorbar (an IDLgrAxis) and giving that up, I found a workaround with a lotta help from Martin Shultz's logLevels fn.

```
oColorBar = Obj_New('HColorBar', $
  Palette=oColorPalette, $
  Range=cbarRange, $
  Title=colorBarTitle, $
  Position=[cbBottomLeft[0], cbBottomLeft[1], $
    cbTopRight[0], cbTopRight[1]], $
  COLOR=axisColor)
```

```
if (keyword_set(log)) then begin
  ;//must alter the colorbar's text.
  ; logLevels() fn. defaults to .1 if I don't set
  ; it explicitly, too hi for me
  if (cbarRange[0] le 0.0) then minLogVal = 0.01 $
  else minLogVal = cbarRange[0]
  maxLogVal = cbarRange[1]
```

```
;get my string of log values, and formatted nicely too
```

```
logtext = strtrim(string(logLevels(MIN=minLogVal, MAX=maxLogVal,  
/fine), FORMAT='(f10.2)'), 2)
```

```
;//only show the decades, not the in-betweeners  
idx = where((indgen(n_elements(logtext)) mod 3) eq 0, count)  
if (count gt 0) then begin  
  temp = reverse(logtext)  
  temp[1:*] = "" ;keep the last entry, set rest to "  
  temp = reverse(temp)  
  temp[idx] = logtext[idx]  
  logtext = temp  
endif
```

```
;//set new properties  
oColorBar->setProperty, MAJOR=n_elements(logtext)  
oColorBar->getProperty, TEXT=oAxisText  
oAxisText->setProperty, STRINGS=logtext  
endif
```

Viola! The only problem is that the scale actually only goes up to maxLogVal, the pretty logged values returned by logLevels(), not my actual max of my data. Eg data ranges [0,65], the axis text will look like

0.01 0.10 1.00 10.00 50.00

when it should be something like

0.01 0.10 1.00 10.00 65.00

The short-spacing and misalignment at the end is intentional. I can't just replace the 50 at the end with 65, because 65 > 50 so it's spacing from the value to its left (10.00) should be a bit more than for 50.00. The next even spaced entry would, of course, be 100.00. Any takers on a solution?

Maybe Dave will add a LOG keyword and slap this code in so's I won't have to copy it into every program that I'll use it.;

t

Subject: Re: log scale of data coloring of IDLgrVolume object, not the axes
Posted by [David Fanning](#) on Sat, 09 Feb 2002 04:12:15 GMT
[View Forum Message](#) <> [Reply to Message](#)

Todd Bowers (tbowers0@yahoo.com) writes:

> Maybe Dave will add a LOG keyword and slap this code in so's I won't
> have to copy it into every program that I'll use it.;)

Maybe, but I'm just going on a trip with my son
to look for the most expensive college. I'll put
it on my list, but you may have to remind me when
I get back. I have a feeling I'm going to feel
depressed and not like doing much programming. :-(

Cheers,

David

--

David W. Fanning, Ph.D.
Fanning Software Consulting
Phone: 970-221-0438, E-mail: david@dfanning.com
Coyote's Guide to IDL Programming: <http://www.dfanning.com/>
Toll-Free IDL Book Orders: 1-888-461-0155
