
Subject: Re: HELP: Linux can't run IDL_LMGRD
Posted by [Bernard Puc](#) on Mon, 29 Jan 2001 18:28:13 GMT
[View Forum Message](#) <> [Reply to Message](#)

Mark Elliott wrote:

>
> Has anyone had the following error:
>
> I have RedHat 7 Linux on a Pentium III, and when I run
> \$IDL_DIR/bin/lmgrd
> I am told:
>
> idl_lmgrd: No such file or directory
>
> Yet, the executable (\$IDL_DIR/bin/bin.linux.x86/idl_lmgrd) is there.
> The unix "file" command says:
>
> idl_lmgrd: ELF 32-bit LSB executable, Intel 80386, version 1,
> dynamically linked (uses shared libs), stripped
>
> Compare this with the IDL executable itself:
>
> idl: ELF 32-bit LSB executable, Intel 80386, version 1, dynamically
> linked (uses shared libs), not stripped
>
> Both have the same permissions:
>
> -rwxr-xr-x 3 root users 1308339 Sep 26 11:09 idl*
> -rwxr-xr-x 1 root users 414956 Sep 26 11:09 idl_lmgrd*
>
> This is NOT a path or IDL environment problem. I can't even run
> idl_lmgrd by hand like:
>
> csh> /usr/local/lib/idl_5.4/bin/bin.linux.x86/idl_lmgrd
>
> I get:
>
> /usr/local/lib/idl_5.4/bin/bin.linux.x86/idl_lmgrd: Command not found.
>
> Any help GREATLY appreciated.
> Mark.
>
> --

Hi Mark,

The quick answer is that you should run this command which is a shell script:

/usr/local/rsi/idl_5.4/bin/idl_lmgrd

Open it in a text editor and you'll see that it handles the call to

/usr/local/lib/idl_5.4/bin/bin.linux.x86/idl_lmgrd

--

Bernard Puc

bpuc@va.aetc.com

(703) 413-0500

AETC, INC.

1225 Jefferson Davis Highway #800

Arlington, VA 22202

Subject: Re: HELP: Linux can't run IDL_LMGRD

Posted by [plugge](#) on Tue, 30 Jan 2001 08:12:53 GMT

[View Forum Message](#) <> [Reply to Message](#)

In article <3A75AE42.76537AF@vuesonix.com>, Mark Elliott <mark@vuesonix.com> writes:
>Has anyone had the following error:

yes :-)))

>I have RedHat 7 Linux on a Pentium III, and when I run

>\$IDL_DIR/bin/lmgrd

>I am told:

>

>idl_lmgrd: No such file or directory

>

>Yet, the executable (\$IDL_DIR/bin/bin.linux.x86/idl_lmgrd) is there.

>The unix "file" command says:

>

>idl_lmgrd: ELF 32-bit LSB executable, Intel 80386, version 1,

>dynamically linked (uses shared libs), stripped

>

>Compare this with the IDL executable itself:

>

>idl: ELF 32-bit LSB executable, Intel 80386, version 1, dynamically

>linked (uses shared libs), not stripped

>

>Both have the same permissions:

>

>-rwxr-xr-x 3 root users 1308339 Sep 26 11:09 idl*

>-rwxr-xr-x 1 root users 414956 Sep 26 11:09 idl_lmgrd*

>

>This is NOT a path or IDL environment problem. I can't even run

>idl_lmgrd by hand like:

>

```
|>csh> /usr/local/lib/idl_5.4/bin/bin.linux.x86/idl_lmgrd  
|>  
|>I get:  
|>  
|>/usr/local/lib/idl_5.4/bin/bin.linux.x86/idl_lmgrd: Command not found.  
|>
```

Mark,

Do you have the old libc5.so installed on your system? I had the same problem, but after installing libc5, lmgrd runs fine.

Best regards

Michael Plugge
