
Subject: Re: default window size
Posted by [Rick Towler](#) on Wed, 08 May 2002 04:34:08 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Win32, it is set in the registry keys:

HKEY_LOCAL_MACHINE/SOFTWARE/Research Systems, Inc./IDL/0/IDL
DLL/HGraphicWind
HKEY_LOCAL_MACHINE/SOFTWARE/Research Systems, Inc./IDL/0/IDL
DLL/WGraphicWind

Note that the "0" refers to the IDL installation and may differ on your machine.

For Unix, I would assume there is a text config file somewhere. I would guess there would be something similar on Mac.

You could change them all programmatically (if that is what you want to do). The config files could be read and rewritten (depending on permissions), and on windows you could craft a .reg file and then execute regedit to modify the key. You could also write a simple .dln for windows to add/edit reg keys.

-Rick

"Reimar Bauer" <r.bauer@fz-juelich.de> wrote in message
news:3CD782C0.E3842473@fz-juelich.de...

> Hi,
>
> By idlde preferences it is possible to set a default window size
> e.g. XSIZE=200, YSIZE=200.
>
> !D.WINDOW.XSIZE and !D.WINDOW.YSIZE is readonly.
>
> Where did idlde set these sizes?
>
> regards
> Reimar
>
> --
> Reimar Bauer
>
> Institut fuer Stratosphaerische Chemie (ICG-I)
> Forschungszentrum Juelich
> email: R.Bauer@fz-juelich.de
> -----
> a IDL library at Forschungszentrum Juelich

> http://www.fz-juelich.de/icg/icg1/idl_icglib/idl_lib_intro.html
> =====

Subject: Re: default window size
Posted by [hradilv](#) on Wed, 08 May 2002 20:24:50 GMT
[View Forum Message](#) <> [Reply to Message](#)

"Rick Towler" <tsehai@attbi.com> once stated in
news:4V1C8.150792\$CH.20989@rwcrcnsc52.ops.asp.att.net:

> On Win32, it is set in the registry keys:
>
> HKEY_LOCAL_MACHINE/SOFTWARE/Research Systems, Inc./IDL/0/IDL
> DLL/HGraphicWind
> HKEY_LOCAL_MACHINE/SOFTWARE/Research Systems, Inc./IDL/0/IDL
> DLL/WGraphicWind
>
> Note that the "0" refers to the IDL installation and may differ on
> your machine.
>
> For Unix, I would assume there is a text config file somewhere. I
> would guess there would be something similar on Mac.
>
> You could change them all programmatically (if that is what you want
> to do). The config files could be read and rewritten (depending on
> permissions), and on windows you could craft a .reg file and then
> execute regedit to modify the key. You could also write a simple .dlm
> for windows to add/edit reg keys.
>
> -Rick
>
>
> "Reimar Bauer" <r.bauer@fz-juelich.de> wrote in message
> news:3CD782C0.E3842473@fz-juelich.de...
>> Hi,
>>
>> By idlde preferences it is possible to set a default window size
>> e.g. XSIZE=200, YSIZE=200.
>>
>> !D.WINDOW.XSIZE and !D.WINDOW.YSIZE is readonly.
>>
>> Where did idlde set these sizes?
>>
>> regards
>> Reimar
>>
>> --

```
>> Reimar Bauer
>>
>> Institut fuer Stratosphaerische Chemie (ICG-I)
>> Forschungszentrum Juelich
>> email: R.Bauer@fz-juelich.de
>> -----
>>      a IDL library at ForschungsZentrum Juelich
>>      http://www.fz-juelich.de/icg/icg1/idl_icglib/idl_lib_intro.html
>> =====
>
>
>
```

From http://www.designmatrix.com/services/XResources_example.html use ->

!---- Graphics window dimensions. IDL defaults are 512 high and 640 wide.
Idl.graphicsWindowHeight: 400
Idl.graphicsWindowWidth: 400

these can be put into \$HOME/.Xdefaults or elsewhere as noted in the above web-page.
