
Subject: Annoying message about X11 Resources on Solaris.

Posted by [JJ](#) on Mon, 29 Jan 2007 19:55:14 GMT

[View Forum Message](#) <> [Reply to Message](#)

I recently upgraded from IDL 6.2 to 6.3 on a Solaris 8 platform, and now when I open an IDL window the first time, I get the following messages:

```
% idl.graphicsWindowWidth X11 resource was used by older versions of IDL
to default width of a graphics
  window, but is ignored by this version. It is present and has a value
of 640 which does not agree
  with the value of the IDL_GR_X_WIDTH preference (900). Set the
IDL_GR_X_WIDTH preference to 640 if
  you wish to use this value. Set the IDL_PREF_OBSOLETE_WARN preference
to False if you wish to
  disable these warning messages in the future.
% idl.graphicsWindowHeight X11 resource was used by older versions of
IDL to default height of a
  graphics window, but is ignored by this version. It is present and
has a value of 512 which does
  not agree with the value of the IDL_GR_X_HEIGHT preference (600). Set
the IDL_GR_X_HEIGHT
  preference to 512 if you wish to use this value. Set the
IDL_PREF_OBSOLETE_WARN preference to False
  if you wish to disable these warning messages in the future.
% idl.graphicsWindow14Screen X11 resource was used by older versions of
IDL to set graphics windows to
  1/4 of the screen size, but is ignored by this version. It is present
and has a value of True which
  does not agree with the value of the IDL_GR_X_QSCREEN preference
(False). Set the IDL_GR_X_QSCREEN
  preference to True if you wish to use this value. Set the
IDL_PREF_OBSOLETE_WARN preference to
  False if you wish to disable these warning messages in the future.
```

Granted, I could set the IDL_PREF_OBSOLETE_WARN preference to False and I wouldn't have to see these annoying messages, but darnit, I want to find out where these preferences are being set and just remove them at the source. I don't have a .Xdefaults file, they're not set in my .idlde file, and other user's on the same machine don't exhibit this problem. I can manage to remove them using an xrdp command, but they're back next time I log in.

Where could these resources possibly be getting set????

Thanks.

-Jonathan
