
Subject: itools crash

Posted by [laxsri](#) on Thu, 27 Nov 2008 22:54:42 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi all,

I am a new user and I am trying to use iplot. Whenever I invoke iplot/itools, the system crashes. I am unable to figure out why this is happening. I appreciate any help. The details are as follows:

IDL Version 6.4 (linux x86 m32). (c) 2007, ITT Visual Information Solutions
Installation number: 97789-6.

Linux version 2.6.9-78.0.1.ELsmp (brewbuilder@ls20-bc2-13.build.redhat.com) (gcc version 3.4.6 20060404 (Red Hat 3.4.6-10))

Thank you,

Lakshmi

Subject: Re: itools crash

Posted by [nemoz](#) on Mon, 15 Dec 2008 16:27:14 GMT

[View Forum Message](#) <> [Reply to Message](#)

On Nov 27, 11:54 pm, lax...@gmail.com wrote:

> Hi all,
>
> I am a new user and I am trying to use iplot. Whenever I invoke iplot/
> itools, the system crashes. I am unable to figure out why this is
> happening. I appreciate any help. The details are as follows:
>
> IDL Version 6.4 (linux x86 m32). (c) 2007, ITT Visual Information
> Solutions
> Installation number: 97789-6.
>
> Linux version 2.6.9-78.0.1.ELsmp (brewbuilder@ls20-
> bc2-13.build.redhat.com) (gcc version 3.4.6 20060404 (Red Hat
> 3.4.6-10))
>
> Thank you,
>
> Lakshmi

Hi,

Try to get read of hardware rendering:

IDL> pref_set, 'IDL_GR_X_RENDERER', 1, /COMMIT

Christian

Subject: Re: itools crash

Posted by [laxsri](#) on Tue, 16 Dec 2008 20:41:26 GMT

[View Forum Message](#) <> [Reply to Message](#)

Hi,

> Try to get read of hardware rendering:
> IDL> pref_set, 'IDL_GR_X_RENDERER', 1, /COMMIT

Thanks! It worked!!

Lakshmi

> Christian
