Subject: Specifying a line feed Posted by mbrown on Wed, 17 Jan 1996 08:00:00 GMT

View Forum Message <> Reply to Message

Can someone tell me how to print a linefeed character using PRINTF in IDL? I'm trying to print out text to my HP, but since the buffer doesn't get full, I have to hit the button on the printer to get the printout. Thanks.

Myron.

Myron Brown mbrown@olie.wvitcoe.wvnet.edu

Subject: Re: Specifying a line feed

Posted by hahn on Thu, 18 Jan 1996 08:00:00 GMT

View Forum Message <> Reply to Message

mbrown@olie.wvitcoe.wvnet.edu (Myron Brown) wrote:

- > Can someone tell me how to print a linefeed character
- > using PRINTF in IDL?

PrintF automatically generates a linefeed.

- > I'm trying to print out text to my
- > HP, but since the buffer doesn't get full, I have to hit
- > the button on the printer to get the printout. Thanks.

I guess you need a form feed! Formfeed on a ASCII printer is 00001100 binary, decimal 12, so you may add

PrintF, String(12B)

after your last PrintF statement.

> Myron.

- > ------
- > Myron Brown
- > mbrown@olie.wvitcoe.wvnet.edu

Norbert Hahn

Subject: Re: Specifying a line feed Posted by M.W.Gardner on Thu, 18 Jan 1996 08:00:00 GMT

View Forum Message <> Reply to Message

mbrown@olie.wvitcoe.wvnet.edu (Myron Brown) wrote:

- > Can someone tell me how to print a linefeed character
- > using PRINTF in IDL? I'm trying to print out text to my
- > HP, but since the buffer doesn't get full, I have to hit
- > the button on the printer to get the printout. Thanks.

>

Try:

printf("%8f%8d....%8f\n",a,b...,c) $\Lambda\Lambda$

Hope that is what you need.

Matt

----> Matt Gardner EMAIL->m.W.gardner@uea.ac.uk PHONE->+44- 1603-592041 School of Environmental Science, University of East Anglia, Norwich, NR4 7TJ, UK

opinions are mine - http://www.uea.ac.uk/~e449