
Subject: Re: Open VMS and PV-WAVE question:
Posted by [Ferry Bolhar-Nordenka](#) on Mon, 10 Mar 1997 08:00:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

questionsrus wrote:

>
> Howdy!
>
> When a user logs on, we would like our DEC 3000 to automatically run a WAVE
> program, as well as automatically log the user off when they exit the WAVE
> program.
>
> We are using OPEN VMS 6.2 and PV-WAVE 6.01.
>
> Please reply via e-mail: dandenault@tip.nrl.navy.mil
>
> Cheers-
> Pat

o) Set the RESTRICTED and DISCTLY flags in the user's account:

o) Use this procedure as the user's login command (LGICMD):

```
$ SET NOCONTROL=(T,Y)
$ SET NOON
$ DEFINE/USER SYS$INPUT SYS$COMMAND
$ RUN WAVE ! or whatever you want
$ LOGOUT
```

The DEFINE/USER command is required only if the WAVE program requires interactive input.

Greetings, Ferry

--

Magistrat der Stadt Wien (MA-14) A - 1010 Vienna (Austria)
Phone: 0222/4000/98632 E-Mail: bol@adv.magwien.gv.at

"Wenn hier einer schuld ist, dann immer nur der Computer."

Subject: Re: Open VMS and PV-WAVE question:
Posted by [leinberger](#) on Tue, 11 Mar 1997 08:00:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

In article <5fqh8t\$snp\$1@ra.nrl.navy.mil>, p@hetic.com (questionsrus) writes:

> Howdy!
>
> When a user logs on, we would like our DEC 3000 to automatically run a WAVE
> program, as well as automatically log the user off when they exit the WAVE
> program.
>
> We are using OPEN VMS 6.2 and PV-WAVE 6.01.
>
> Please reply via e-mail: dandenault@tip.nrl.navy.mil
>
> Cheers-
> Pat
>
What you probably want to do is to set up a captive account.
Have a look at the System Manager's Manual from the VMS DocSet.
It's all there.

Cheers

Uwe
