
Subject: Re: idlwave mode for emacs/xemacs?
Posted by [luthi](#) on Tue, 27 Jul 1999 07:00:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

Kristine

I have IDLWAVE mode perfectly working with emacs 20.3. Have you followed the installation instructions, especially the additions to your ~/.emacs file. This should look somewhat like the following lines of code, but I guess that only the first 3 lines are essential for IDLWAVE-mode to work, the rest is for convenience.

Hope this helps!

Cheers Martin

```
;; idlwave- mode
(autoload 'idlwave-mode "idlwave" "IDLWAVE Mode" t)
(autoload 'idlwave-shell "idlwave-shell" "IDLWAVE Shell" t)
(setq auto-mode-alist (cons '("\\.pro\\") . idlwave-mode) auto-mode-alist))

(add-hook 'idlwave-mode-hook
  (function
    (lambda ()
      (setq          ; Set options here
        idlwave-expand-generic-end t)
      (define-key idlwave-mode-map
        [M-RET]
        'hippie-expand)
      )))

(add-hook 'idlwave-shell-mode-hook
  (function
    (lambda ()
      (setq          ; Set options here
        idlwave-shell-prompt-pattern "^WAVE> " ; see def below
        idlwave-shell-overlay-arrow "=>"
        idlwave-shell-fix-inserted-breaks t
        )
      ;; Run other functions here
      (idlwave-action-and-binding idlwave-sysvar '(capitalize-word 1) t)
      )))
;; These variables are used by `idlwave-shell' before the hook is run. So
;; they must be set explicitly before calling `idlwave-shell'.
(setq idlwave-shell-explicit-file-name "/net/artemis2/soft/graf/vni/wave/bin/wave")
(setq idlwave-shell-process-name "/net/artemis2/soft/graf/vni/wave/bin/wave")
```

(autoload 'idlwave-shell "idlwave-shell" "Run IDL as an inferior process" t)

--

=====
Martin Luethi Tel. +41 1 632 40 92
Glaciology Section Fax. +41 1 632 11 92
VAW ETH Zuerich
CH-8092 Zuerich mail luthi@vaw.baum.ethz.ch
Switzerland
=====
