

---

Subject: default window size

Posted by [R.Bauer](#) on Tue, 07 May 2002 07:31:12 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

Hi,

By idlde preferences it is possible to set a default window size  
e.g. XSIZE=200, YSIZE=200.

!D.WINDOW.XSIZE and !D.WINDOW.YSIZE is readonly.

Where did idlde set these sizes?

regards  
Reimar

--  
Reimar Bauer

Institut fuer Stratosphaerische Chemie (ICG-I)  
Forschungszentrum Juelich  
email: [R.Bauer@fz-juelich.de](mailto:R.Bauer@fz-juelich.de)

-----  
a IDL library at ForschungsZentrum Juelich  
[http://www.fz-juelich.de/icg/icg1/idl\\_icglib/idl\\_lib\\_intro.html](http://www.fz-juelich.de/icg/icg1/idl_icglib/idl_lib_intro.html)

---

Subject: Re: default window size

Posted by [R.Bauer](#) on Thu, 09 May 2002 10:17:34 GMT

[View Forum Message](#) <> [Reply to Message](#)

---

perfect !

thanks  
Reimar

hradilv wrote:

>  
> "Rick Towler" <[tsehai@attbi.com](mailto:tsehai@attbi.com)> once stated in  
> [news:4V1C8.150792\\$CH.20989@rwcrrnc52.ops.asp.att.net](mailto:news:4V1C8.150792$CH.20989@rwcrrnc52.ops.asp.att.net):  
>  
>> On Win32, it is set in the registry keys:  
>>  
>> HKEY\_LOCAL\_MACHINE/SOFTWARE/Research Systems, Inc./IDL/0/IDL  
>> DLL/HGraphicWind  
>> HKEY\_LOCAL\_MACHINE/SOFTWARE/Research Systems, Inc./IDL/0/IDL

```

>> DLL/WGraphicWind
>>
>> Note that the "0" refers to the IDL installation and may differ on
>> your machine.
>>
>> For Unix, I would assume there is a text config file somewhere. I
>> would guess there would be something similar on Mac.
>>
>> You could change them all programmatically (if that is what you want
>> to do). The config files could be read and rewritten (depending on
>> permissions), and on windows you could craft a .reg file and then
>> execute regedit to modify the key. You could also write a simple .dlm
>> for windows to add/edit reg keys.
>>
>> -Rick
>>
>>
>> "Reimar Bauer" <r.bauer@fz-juelich.de> wrote in message
>> news:3CD782C0.E3842473@fz-juelich.de...
>>> Hi,
>>>
>>> By idlde preferences it is possible to set a default window size
>>> e.g. XSIZE=200, YSIZE=200.
>>>
>>> !D.WINDOW.XSIZE and !D.WINDOW.YSIZE is readonly.
>>>
>>> Where did idlde set these sizes?
>>>
>>> regards
>>> Reimar
>>>
>>> --
>>> Reimar Bauer
>>>
>>> Institut fuer Stratosphaerische Chemie (ICG-I)
>>> Forschungszentrum Juelich
>>> email: R.Bauer@fz-juelich.de
>>> -----
>>> a IDL library at ForschungsZentrum Juelich
>>> http://www.fz-juelich.de/icg/icg1/idl_icglib/idl_lib_intro.h tml
>>> =====
>>
>>
>>
> From http://www.designmatrix.com/services/XResources_example.html use ->
>
> !---- Graphics window dimensions. IDL defaults are 512 high and 640 wide.
> Idl.graphicsWindowHeight: 400

```

> Idl.graphicsWindowWidth: 400  
>  
> these can be put into \$HOME/.Xdefaults or elsewhere as noted in the above  
> web-page.

--  
Reimar Bauer

Institut fuer Stratosphaerische Chemie (ICG-I)  
Forschungszentrum Juelich  
email: R.Bauer@fz-juelich.de

-----  
a IDL library at ForschungsZentrum Juelich  
[http://www.fz-juelich.de/icg/icg1/idl\\_icglib/idl\\_lib\\_intro.h tml](http://www.fz-juelich.de/icg/icg1/idl_icglib/idl_lib_intro.h tml)  
=====

---