
Subject: language change in IDL
Posted by [hadi](#) on Mon, 09 Jul 2012 05:33:17 GMT
[View Forum Message](#) <> [Reply to Message](#)

Dear All

I have problem to change the Japanese language to English language. I added -nl en in the end of idle.exe but it dosent change the language.

like this

"C:\Program Files\Exelis\IDL82\bin\bin.x86\idlde.exe"-nl en

i tried more to change the position of -nl en befor and after punctuation (").

But no work. Please help me about this problem

Subject: Re: language change in IDL
Posted by [Tian](#) on Fri, 13 Jul 2012 12:43:29 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Monday, July 9, 2012 1:33:17 PM UTC+8, fada...@gmail.com wrote:

> Dear All

> I have problem to change the Japanese language to English language. I added -nl en in the end of idle.exe but it dosent change the language.

> like this

> "C:\Program Files\Exelis\IDL82\bin\bin.x86\idlde.exe"-nl en

> i tried more to change the position of -nl en befor and after punctuation (").

> But no work. Please help me about this problem

Hi,i think you can rigth click the idl shorcut ,choose properties ,shortcut,in the target label,add " -nl en".Just like this "C:\Program Files\Exelis\IDL82\bin\bin.x86\idlde.exe" -nl en
mabe it works well

Subject: Re: language change in IDL
Posted by [hadi](#) on Tue, 17 Jul 2012 02:45:43 GMT
[View Forum Message](#) <> [Reply to Message](#)

On Friday, July 13, 2012 9:43:29 PM UTC+9, Tian wrote:

> On Monday, July 9, 2012 1:33:17 PM UTC+8, fada...@gmail.com wrote:

> > Dear All

> > I have problem to change the Japanese language to English language. I added -nl en in the end of idle.exe but it dosent change the language.

> > like this

> > &quot;C:\Program Files\Exelis\IDL82\bin\bin.x86\idlde.exe&quot;-nl en

> > i tried more to change the position of -nl en befor and after punctuation (&quot;).

> > But no work. Please help me about this problem

>

> Hi,i think you can rigth click the idl shorcut ,choose properties ,shortcut,in the target label,add "-nl en".Just like this "C:\Program Files\Exelis\IDL82\bin\bin.x86\idlde.exe"

-nl en
> mabe it works well

Hi
it was work very well. Thank you alot.
Best, Hadi
