## Subject: Pointers to arrays in widget programs (PV-Wave and IDL) Posted by rep2857 on Wed, 07 Dec 1994 20:35:49 GMT

View Forum Message <> Reply to Message

Hi all -

I've been using IDL for a couple years and just switched to PV-Wave. One thing that I'd like to figure out how to do is use the Userdata option in Wave to pass a pointer to an array which can be resized. Here's what I mean in terms of IDL widget syntax, and what I thought would work in WaveWidget syntax. I haven't been able to get this to work correctly with WaveWidgets, though. The following were keyed in on the fly and should be considered a concept, not actual running code.

```
IDL Version 3.6, Sun SS-10, SunOS 4.1.3.
Wave CL Version 4.2, Sun SS-10, SunOS 4.1.3.
IDL:
pro test
ptr = widget_base(); unrealized base for use with UValue
fptr = widget_base(Group=ptr); unrealized base for use with UValue
fdata = 0; will eventually hold array of varying sizes
info = {
 data:0L, $
 fptr:fptr}
; commands and widget layouts deleted
Widget_Control, fptr, Set_UValue=fdata
Widget_Control, ptr, Set_UValue=info
end
pro test event, event
Widget_Control, event.top, Get_UValue=ptr
Widget_Control, ptr, Get_UValue=info, /No_Copy
Widget_Control, info.fptr, Get_UValue=fdata, /No_Copy
: commands deleted
; declare xsize and ysize based on some kind of data
; could be different size each time
fdata = bytarr(xsize, ysize)
Widget_Control, info.fptr, Set_UValue=fdata, /No_Copy
Widget Control, ptr, Set UValue=info, /No Copy
end
Wave:
pro test
splash = WwInit('qmr', 'Qmr', bboard, /Board)
base = WwMainWindow(splash, layout, /Form)
fptr = WwMainWindow(layout)
abutton = WwButtonBox(layout, 'Button Label', 'test event')
```

```
; commands and widget layouts deleted
fdata = 0
info = \{, \$
 data:0L, $
 abutton:abutton, $
 base:base, $
 fptr:fptr}
; if I remember correctly this next line will fail during compile
status = WwSetValue(info.fptr, Userdata=fdata)
status = WwSetValue(base, Userdata=info)
end
pro test_event, wid, data
info = WwGetValue(wid, /Userdata)
fdata = WwGetValue(info.fptr, /Userdata)
; unfortunately base and fdata are identical after this
: I would like fdata to be whatever I had stored in the userdata
; for base.fptr on a previous instance, typically an image array
fdata = bytarr(xsize, ysize)
status = WwSetValue(info.fptr, Userdata=fdata)
end
```

I was trying to put an application together for a demo in a very short time, and will happily concede to making a stupid mistake if someone can show me how to do this. In the interim, I've coded the demo with a short common block, which I would rather avoid. I can provide more thorough code examples through email if necessary. I've been able to assign values and structures using the above type of declarations, but I can't change the dimensions without giving the program fits.

Thanks.

Mike Schienle Hughes Santa Barbara Research Center rep2857@sbsun0010.sbrc.hac.com 75 Coromar Drive, M/S B28/87

Voice: (805)562-7466 Fax: (805)562-7881 Goleta, CA 93117