Subject: Re: Use IDL6.0 to read Fortran 90 written data Posted by Nianming Zuo on Wed, 08 Aug 2007 03:52:58 GMT

View Forum Message <> Reply to Message

Thank you, Paul, David, Mike, chl and other guys. I have read the links (and other related links), and it is really helpful for my puzzels.

And now, I have another problem. (The following are on MS Windows XP(sp2))

IDL6.0 can not read data saved by gcc3.4. (Mingw32)

in "gccfile.dat", I saved a seriers of data, including int and float type, using gf = fopen("gccfile.dat", "w"); fwrite(NLAM, sizeof(int),1, gf); //repeat this sentence to store several vars, NLAM,R,D,H,ALAM0,ALAM1,DLAM, with different type.

Now, I want to read datas in "gccfile.dat", and I have tried many methods.

Way 1:

openr, lun, "gccfile.dat", /GET_LUN readu,lun,NLAM,R,D,H,ALAM0,ALAM1,DLAM print, NLAM,R,D,H,ALAM0,ALAM1,DLAM

It prints strange data like 3.36641e+038, and prompts:

% Program caused arithmetic error: Floating underflow

% Program caused arithmetic error: Floating illegal operand

Way 2: (learn from this forum. THANKS:))

openr, lun, "gccfile.dat", /GET_LUN, /SWAP_ENDIAN readu,lun,NLAM,R,D,H,ALAM0,ALAM1,DLAM print, NLAM,R,D,H,ALAM0,ALAM1,DLAM

It still prints the garbage!

I have tested the endian-ness things with (from Paul. Thanks):

openr,lun,'shepp.sgm', /GET_LUN; "shepp.sgm" is my file.; -- Check the record size
RecordSize = 10000L * 4L
RecordSize_Test = 0L
READU, lun, RecordSize_Test
IF (RecordSize Test NE RecordSize) THEN \$

```
Swap = 1 \$
ELSE $
  Swap = 0
: -- Close the file
FREE_LUN, lun
print, "Swap", Swap
; The above Swap turns out 1. So swap is necessary.
Way 3:
openr, lun, "gccfile.dat", /GET_LUN; Without /SWAP_ENDIAN
readu,lun,NLAM,R,D,H,ALAM0,ALAM1,DLAM
NLAM = SWAP\_ENDIAN(NLAM)
print, NLAM, R, D, H, ALAMO, ALAM1, DLAM
Amazingly, NLAM (integer) is wrong, and other vars (float) are right!
I am totally confused by its behavious!
Additionally, I have tried another ways, and did't take effect.
byteorder, NLAM,R,D,H,ALAM0,ALAM1,DLAM, /Iswap
One suggested "binread" function, but it doesn't exist in IDL6.0.
Thanks,
Tony
On 87, 839, Paul van Delst <Paul.vanDe...@noaa.gov> wrote:
> Nianming Zuo wrote:
>> Dear all.
>> I have sufferred file read/write problems between Fortran 90/95 and
>> IDL 6.0.
>> My Fortran compiler:
>> Silverfrost ftn95, Compatable for Fortran 77/90/95
>> http://www.silverfrost.com/12/ftn95/ftn95_feature_details.as p
>> IDL 6.0 (Interactive Data Language, RSI)
>
```

```
>> Both are in MS Windows XP(sp2) OS system.
>> Write data to a file by use of Fortran:
>> dimension dat(m, n)
>> !...... Manipulations..., matrix dat(m, n) is float
>> open(unit=11, file="file.dat", form="unformatted")
>> write(11) dat
>> !.....
>>! The above are really f77 code, so I guess it is related to Compiler.
>> Read the data above by IDL6.0: (Way 1)
>> dat = fltarr(m.n)
>> openr, 1, 'file.dat'
>> readu, 1, b, dat, b
>> In "readu, 1, b, dat, b", the "b"s are used to skip the record area in
>> Fortran data format.
>> Unfortunately, it can not get the right result, and prompts "End of
>> the file"
>> I have also tried another way in IDL: (Way 2)
>> dat = fltarr(m,n)
>> openr, 1, 'file.dat' /f77_unformatted
>> readu, 1, dat
>> But, it prompts,
>> "% READU: Corrupted f77 unformatted file detected."
>> For the above Fortran code, when it is compiled by q77, IDL can read it
>> by Way 2.
>> So, I doubt that different compilers give different response to the
>> standard Fortran sentences?
>> Since there is no f90_unformatted or f95_unformatted, f77/f90/f95 will
>> produce the same record for the "open-write" sentence.
>> Now, how can I read ftn95 compiled output data by IDL6.0? I have
>> searched this forum, but without any desirable results.
  Have a lookee at:
>
  http://groups.google.com/group/comp.lang.idl-pvwave/browse_t hread/thr...
  (Crikey that's a long link)
>
 cheers,
>
> paulv-
```

```
>
```

Page 4 of 4 ---- Generated from comp.lang.idl-pvwave archive