
Subject: openr,/xdr & readu,structure problems
Posted by [R.G. Stockwell](#) on Tue, 09 Nov 1999 08:00:00 GMT
[View Forum Message](#) <> [Reply to Message](#)

Greetings,
I'd appreciate a hint or two is someone has
ran into a problem similar to the one that I have.
(A deja.com search hasn't helped me.)

I have received a new "xdr" data file that I'm trying
to read in using idl5.2.1 on winnt.
(also tried on idl5.3beta, same problem)

The problem is that when I read in to a defined structure,
it sometimes (rarely) reads in a huge chunk. To be specific,
the structure read is only 92 bytes, but the READU command
seems to send the filepointer to the end of the file or
something like that). The structure will now contain
junk information.

I suspect that this is because of my platform,
since this code works fine on an SGI, but not on WinNT.
Anyone know why this is happening, and how to handle
it properly?

----- more detail -----

I define a structure containing floats, integers and
arrays of integers, and arrays of floats (no strings, no bytes).
The size of the structure is 15 tags, size = 92 bytes.
This corresponds to a 104 byte chunk in the xdr-file.

Here is the (edited) code for the structure:

```
int = 0 ; integer type (2-byte integer)
time_arr = intarr(6) ; time array
time_ind = 0L ; unix time index
snr_pow_arr = fltarr(no_channels > 1) ; snr and power array
flt = 0.
last_analysis = {$
TIME : time_arr, $ ; record time - real
UNIX_TIME : time_ind, $ ; record time - unix
RANGE : flt,$ ; record range
ERROR : int,$ ; error code
APP_VEL : fltarr(2),$ ; apparent velocity
VELOCITY : fltarr(2),$ ; true velocity
VERT_VEL : flt,$ ; vertical velocity
FAD_TIME : flt,$ ; fading time
```

```

CORR_FAD_TIME : flt,$ ; corrected fading time
PATT_SCALE : flt,$ ; pattern scale
AXIAL_RATIO : flt,$ ; axial ratio
AXIAL_ROT : flt,$ ; axial rotation
PTD : int,$ ; percentage time discrepancy
SNR : snr_pow_arr,$ ; signal to noise ratio
POWER : snr_pow_arr $ ; signal power
}

```

```

print, last_analysis
{
  0 0 0 0 0 0
  0 0.000000 0
  0.000000 0.000000
  0.000000 0.000000
  0.000000 0.000000 0.000000 0.000000 0.000000
0.000000 0
  0.000000 0.000000 0.000000
  0.000000 0.000000 0.000000
}

```

Here are the commands to open and read in the data:

```

openr,readlun,filename,xdr=1,/get_lun ; Input file
fileinfo_before = fstat(readlun)
readu,readlun,last_analysis
fileinfo_after = fstat(readlun)

```

```

-----
-----
---FILE INFO---
-----BEFORE READ-----
** Structure FSTAT, 12 tags, length=36:
UNIT      LONG      100
NAME      STRING    'd:\fca\19990926_fca.fca'
OPEN      BYTE      1
ISATTY    BYTE      0
ISAGUI    BYTE      0
INTERACTIVE  BYTE    0
READ      BYTE      1
WRITE     BYTE      0
TRANSFER_COUNT LONG      0
CUR_PTR   LONG      0
SIZE      LONG      1241760
REC_LEN   LONG      0
-----after READ-----
** Structure FSTAT, 12 tags, length=36:
UNIT      LONG      100

```

NAME	STRING	'd:\fca\19990926_fca.fca'
OPEN	BYTE	1
ISATTY	BYTE	0
ISAGUI	BYTE	0
INTERACTIVE	BYTE	0
READ	BYTE	1
WRITE	BYTE	0
TRANSFER_COUNT	LONG	0
CUR_PTR	LONG	32857
SIZE	LONG	1241760
REC_LEN	LONG	0

The point I am making is that the "after" file pointer is at 32857, when it really should be 104

```
> CUR_PTR      LONG      32857
```

So what is going on?

Thanks a lot,

cheers,

bob

--

R.G. Stockwell

stockwell at co-ra.com

Colorado Research Associates

3380 Mitchell Lane

Sent via Deja.com <http://www.deja.com/>

Before you buy.
