
Subject: Re: METEOSAT navigation

Posted by [Liam E. Gumley](#) on Wed, 23 Apr 2003 14:16:13 GMT

[View Forum Message](#) <> [Reply to Message](#)

"Roberto Hernandez" <rhernandez@euve.org> wrote in message
news:9886e8f4.0304230034.1cec4b91@posting.google.com...

> Hello all,
> I'm trying to overlap coastal boundaries to a METEOSAT image (B
> format, that covers the European, North African and Middle East
> regions) with the MAP_SET command.
> I need to use the native projection -geostationary- and specify the
> LIMIT option as an eight-element vector, although the top pixels are
> on space. I try to substitute them with the extreme coordinates on
> Earth's visible disc, but the boundaries don't match properly.
>
> Any ideas will be appreciated.

You may have better luck with the SCALE keyword for MAP_SET (instead of
LIMIT). As a guide, a map scale of 4E6 corresponds to a map resolution of
1000 meters, assuming 40.0 pixels per centimeter in IDL direct graphics,
i.e.,

```
IDL> print, !d.x_px_cm  
40.0000
```

This value may be slightly different on other platforms. So the trick is to
create a map projection with the appropriate scale, e.g.

```
clat = 0.0  
clon = 140.0 ; longitude for Meteosat 7  
scale = 16E6 ; map resolution of 4000 meters  
map_set, clat, clon, scale=(scale * (!d.x_px_cm / 40.0)), $  
  /orthographic, position=[0.0, 0.0, 1.0, 1.0], /noerase  
map_continents
```

This command assumes the center pixel of the image is at [clat, clon], so it
may not work if the image has been clipped in some way (i.e., it's not a
full disk image).

Another source of information is Kelly Dean's site at

<http://www.cira.colostate.edu/special/csuidl/overview.htm>

that might be helpful.

Cheers,
Liam.
Practical IDL Programming

Subject: Re: METEOSAT navigation

Posted by [Liam E. Gumley](#) on Wed, 23 Apr 2003 14:26:21 GMT

[View Forum Message](#) <> [Reply to Message](#)

"Liam Gumley" <Liam.Gumley@ssec.wisc.edu> wrote in message
news:b8677e\$mfi\$1@news.doit.wisc.edu...

[stuff deleted]

> clon = 140.0 ; longitude for Meteosat 7

Oops, GMS is at 140 East. Meteosat is at 0 degrees longitude.

Cheers,

Liam.

Practical IDL Programming

<http://www.gumley.com>
