Subject: Re: IDL 6.3 Intel in Mac + IDLWAVE + graphics = CRASH Posted by Karl Schultz on Wed, 13 Sep 2006 15:09:35 GMT

View Forum Message <> Reply to Message

On Sun, 10 Sep 2006 23:56:33 -0700, jgc wrote:

```
> Dear All,
>
> IDL 6.3 Intel native is running fine when called from the Xterminal or
> from idlde. However, when run from IDLWAVE it crashes (better
> implodes and collapses) whenever a graphic command is issued. It used
> to be fine with IDL 6.2.
>
> I have tried setting DISPLAY equal to both ":0.0" an ":0", in .bashrc
> and in .MacOSX/environment.plist. Curiosly, if Xwindows is not running
> it looks for it appropriately,
> % PLOT: Unable to connect to X Windows display: :0.0
> % PLOT: Unable to open X Windows display.
       Is your DISPLAY environment variable set correctly?
>
> but when it is running it collapses on every graphic command. Then
> when IDL is recalled, it displays a bus error from the previous
> session.
> If I enquire the system from the xterminal within IDL I get
> IDL> $env
> TERM=xterm
> DISPLAY=:0.0
>
> from IDWAVE, first, I need to call twice the idl shell (C-c C-s is
> undefined on first call), then the environment variables are different:
> IDL> $env
> TERM=dumb
> there is no DISPLAY variable
> Any help in solving this is much appreciated.
> all the best.
> Javier
> IDL 6.3 for Mac OS X for Intel, last release (2 days ago)
> MacBook Pro Intel duo OS X 10.4.7
> GNU Emacs 22.0.50.1
> IDLWAVE 6.0
```

There is a known bug, introduced in 6.3 and fixed in the Next Release, that will cause IDL to crash on OS X if the DISPLAY variable is not set. In most Unix/X environments, IDL is usually launched from a shell running under the control of an X client that has the DISPLAY variable set. So, this is not usually an issue. On OS X however, some people launch IDL from the Terminal app, rather than an xterm, and then run into this problem.

Your solution is to do whatever it is you need to do to get the DISPLAY variable set in the shell environment in which IDLWAVE is running. My wild guess is that you are starting emacs/IDLWAVE from either a Terminal app or some desktop shortcut and you're not getting the DISPLAY variable set.

Karl

Subject: Re: IDL 6.3 Intel in Mac + IDLWAVE + graphics = CRASH Posted by jgc on Wed, 13 Sep 2006 19:08:24 GMT

View Forum Message <> Reply to Message

- > Your solution is to do whatever it is you need to do to get the DISPLAY
- > variable set in the shell environment in which IDLWAVE is running. My
- > wild guess is that you are starting emacs/IDLWAVE from either a Terminal
- > app or some desktop shortcut and you're not getting the DISPLAY variable
- > set.

>

> Karl

That makes sense and it was so simple!

It works beautifully now alias Emacs='/Applications/Emacs.app/Contents/MacOS/Emacs &' and calling it from the xterminal.

Many, many thanks and apologies for being so thick.

Javier

Subject: Re: IDL 6.3 Intel in Mac + IDLWAVE + graphics = CRASH Posted by Edd Edmondson on Thu, 14 Sep 2006 10:21:23 GMT View Forum Message <> Reply to Message

igc <javier_corripio@yahoo.fr> wrote:

- >> Your solution is to do whatever it is you need to do to get the DISPLAY
- >> variable set in the shell environment in which IDLWAVE is running. My
- >> wild guess is that you are starting emacs/IDLWAVE from either a Terminal

- >> app or some desktop shortcut and you're not getting the DISPLAY variable
- >> set
- >>
- >> Karl
- > That makes sense and it was so simple!
- > It works beautifully now
- > alias Emacs='/Applications/Emacs.app/Contents/MacOS/Emacs &'
- > and calling it from the xterminal.

Bit off topic, but you may like to replace that with 'open -a Emacs'. Sort of 'more proper', quicker to type, and will still open Emacs if you decided for some reason to move it to another location.

--Edd

Subject: Re: IDL 6.3 Intel in Mac + IDLWAVE + graphics = CRASH Posted by JD Smith on Tue, 19 Sep 2006 17:26:06 GMT View Forum Message <> Reply to Message

On Wed, 13 Sep 2006 12:08:24 -0700, jgc wrote:

>

- >> Your solution is to do whatever it is you need to do to get the DISPLAY
- >> variable set in the shell environment in which IDLWAVE is running. My
- >> wild guess is that you are starting emacs/IDLWAVE from either a Terminal
- >> app or some desktop shortcut and you're not getting the DISPLAY variable
- >> set.
- >>
- >> Karl

>

> That makes sense and it was so simple!

· ...

- > It works beautifully now
- > alias Emacs='/Applications/Emacs.app/Contents/MacOS/Emacs &'
- > and calling it from the xterminal.

>

> Many, many thanks and apologies for being so thick.

The other option for setting global system-wide environment variables, is to use environment.plist, which would also fix this. This is a "plist" XML type file, but a simple way to set DISPLAY there is like this:

% mkdir ~/.MacOSX

% defaults write ~/.MacOSX/environment DISPLAY:0

Now *all* processes will have this in their environment, no matter how they were opened.

As a side note, if you use fast user switching, :0 may not always be correct here (since each X11 process increments it, e.g. :1 for the second user to run X11 simultaneously). The following trick should work in that case, especially if you have X11 start up automatically on login:

http://lists.sourceforge.jp/mailman/archives/macemacsjp-engl ish/2006-June/000586.html

In IDL, you should check what environment variables are set with:

IDL> print,getenv('DISPLAY')

rather than \$env, since that first starts a shell (which may define environment through configuration files which the IDL process itself does not share).

Another simple fix (for IDL only) would be to put:

setenv, 'DISPLAY=:0'

in your IDL startup file.

BTW, this issue only applies to "Emacs.app" carbon app on OSX, which is run directly by the OS. In that case, IDLWAVE and the IDL process are run in an environment which does not know about X11, which of course IDL needs. Those of you who (like me) still use Emacs under X11 should be fine.

JD