Subject: Re: Problem with dist function in IDL Posted by Michael Galloy on Mon, 13 Aug 2007 00:48:07 GMT

View Forum Message <> Reply to Message

On Aug 12, 8:41 am, ATKT <ankur.trigun...@gmail.com> wrote:

- > Can somebody tell what exactly dist function is doing in IDL
- > e.g x=dist(2,2)
- > 0.000000 1.00000
- > 1.00000 1.41421
- > What is the meaning of this ouput
- > x = dist(4,4)

>	0.000000	1.00000	2.00000	1.00000
>	1.00000	1.41421	2.23607	1.41421
>	2.00000	2.23607	2.82843	2.23607
>	1.00000	1.41421	2.23607	1.41421

>

> I am unable to understand the out put which is being generated.

The online help says this:

"The DIST function creates an array in which each array element value is proportional to its frequency. This array may be used for a variety of purposes, including frequency-domain filtering."

But I think about it in terms of plain Euclidean distance. Each array element's value is the shortest distance to (0, 0) allowing for wrapping around the edges. This has applications in creating kernels for image processing filters (and is simple dataset for examples).

## Mike

--

www.michaelgalloy.com

Subject: Re: Problem with dist function in IDL Posted by Paolo Grigis on Mon, 13 Aug 2007 10:06:59 GMT

View Forum Message <> Reply to Message

## ATKT wrote:

- > Can somebody tell what exactly dist function is doing in IDL
- > e.g x=dist(2,2)
- > 0.000000 1.00000
- > 1.00000 1.41421
- > What is the meaning of this ouput
- > x = dist(4,4)
- > 0.000000 1.00000 2.00000 1.00000 > 1.00000 1.41421 2.23607 1.41421
- > 2.00000 2.23607 2.82843 2.23607

```
1.00000
                 1.41421
                             2.23607
                                         1.41421
>
 I am unable to understand the out put which is being generated.
A graphical representation is also always useful...
loadct,5
tvscl,shift(dist(512,512),256,256)
Ciao.
Paolo
Subject: Re: Problem with dist function in IDL
Posted by cgguido on Wed, 15 Aug 2007 23:23:21 GMT
View Forum Message <> Reply to Message
 A graphical representation is also always useful...
> loadct.5
> tvscl,shift(dist(512,512),256,256)
> Ciao.
> Paolo
Useful, but not sufficient in my case :-(
In the case of dist(4,1), say, how do you get the values 0.00, 1.00,
2.00, 1.00 ?
```

Never quite got it! :-(

G

Subject: Re: Problem with dist function in IDL Posted by Jean H. on Thu, 16 Aug 2007 00:34:52 GMT View Forum Message <> Reply to Message

```
> Useful, but not sufficient in my case :-(
> In the case of dist(4,1), say, how do you get the values 0.00, 1.00,
> 2.00, 1.00 ?
> Never quite got it! :-(
```

> > G

Here is a graphical explanation of Mike's answer:

so, let's create an empty row of size 4

```
[a,b,c,d]
```

then we want to compute the distance from the top left corner to every other cell, what the "dist" function does. To do that, let's assume we have an infinite array: ....,c,d,a,b,c,d,a,b, .....

Then the we can see that from A to B, there is 1 cell (pixel, unit, whatever), from A to C there is 2 cells and from A to D we have either 1 cell (because the beginning of the array is next to the last element of it), or 3 cells (through B and C). Dist() will return the smallest one... so you have dist(4,1) = 0,1,2,1

Now let's make it a tad bigger:

dist(10,10)

The last entry of the array is 1.41. From the first element, one has to jump UP one cell to get to the last row, and LEFT one cell to get to the last column... the distance is therefore 1.41

... jean

Subject: Re: Problem with dist function in IDL Posted by Paolo Grigis on Thu, 16 Aug 2007 10:13:58 GMT View Forum Message <> Reply to Message

## Gianquido Cianci wrote:

```
>> A graphical representation is also always useful...
>>
>> loadct,5
>> tvscl,shift(dist(512,512),256,256)
>>
>> Ciao,
>> Paolo
>
> Useful, but not sufficient in my case :-(
> In the case of dist(4,1), say, how do you get the values 0.00, 1.00,
> 2.00, 1.00 ?
>
> Never quite got it! :-(
```

```
> G
This program (not optimized) reproduces the functionality of DIST:
_____
n=4
m=5
a=dist(n,m)
b=fltarr(n,m)
FOR i=0L,n-1 DO BEGIN
  FOR j=0L,m-1 DO BEGIN
    i2=min([i,n-i])
    j2=min([j,m-j])
    b[i,j]=sqrt(i2^2+j2^2)
  ENDFOR
ENDFOR
-----
So dist[i,j] is the shortest distance from the euclidean
point with coordinates (i,j) to one of the points (0,0),
(0,m), (n,0) or (n,m).
Ciao,
Paolo
```

Subject: Re: Problem with dist function in IDL Posted by David Fanning on Tue, 28 Aug 2007 18:26:37 GMT View Forum Message <> Reply to Message

Paolo\_Grigis writes:

```
> FOR i=0L,n-1 DO BEGIN
    FOR j=0L,m-1 DO BEGIN
>
      i2=min([i,n-i])
>
      j2=min([j,m-j])
      b[i,j]=sqrt(i2^2+j2^2)
>
>
    ENDFOR
> ENDFOR
```

I was just having a look at the BUTTERWORTH filter code in the IDL library, and I notice that the ITTVIS programmer who wrote this function uses the double FOR loop method to create the distance function, rather than DIST.

What do you suppose he knows that we don't!?

Cheers,

David

David Fanning, Ph.D. Fanning Software Consulting, Inc.

Coyote's Guide to IDL Programming: http://www.dfanning.com/

Sepore ma de ni thui. ("Perhaps thou speakest truth.")